



Backing Up the EL-CID Database

The following steps will illustrate how to backup certifications in the EL-CID database. This process may be used to export one or more certifications, or the complete database.

Step 1. Start the EL-CID program. If the Startup EL-CID Wizard window is displayed, click **Cancel** to dismiss this screen.




Step 2. The main screen appears.




Step 3. Click the **New Query** button  on the tool bar.


The **Build Query** window appears and (assuming that you have not disabled it in the Preferences) the **Select Data Item** window automatically appears. If the **Select Data Item** window is displayed, click **Cancel**.




Step 4. The **Build Query** window appears.




Step 5. Select **Certification** using the dropdown list button  for the **Select Record** box.



Step 6. Click the **Run Query** button, or click the **Query Results** tab to execute the query. All Certifications in your Database will appear.




Step 7. Highlight all rows by selecting **Query** on the tool bar, then select **Grid** and **Highlight All** from the drop down list.




NOTE: If only one or more Certifications are to be exported, highlight only those rows that you wish to export. You can hold down the **Ctrl** key and click each row individually.


All Certifications have been selected and will be highlighted.



Step 8. Right-click and select **Export** from the drop down list.




Step 9. The **Export Certification** window appears.




NOTE: The filename defaults to **Certification_AR_09102015.cid** (i.e., Type of file exported_Agency_Date).


Step 10. Click the **Browse** button  to select the directory in which the files will be saved. Select the folder **C:\ElcidData**. Click **Open**.



Step 11. Select the **User** folder. Click **Open**.




The **User** folder is displayed.




NOTE: The name in the **File name** box may be changed at this point. For this example we will keep the default name.


Step 12. Click **Save**. The **Export Certification** window is displayed again showing the path and filename that you selected. Additional information may be entered in the **Description** box.




Step 13. Click **Export**. The **Cover Sheet Classification Markings** window is displayed. Select the appropriate Special Handling Instructions.




Step 14. Click **OK**. The **Save to File – Security Markings** window is displayed.



Step 15. Click **OK**. A **Progress** window is displayed while EL-CID is exporting Certifications, Antennas, Locations, Receivers, and Transmitters. The time it takes depends upon the size of your Database.



Step 16. The **Build Query** window appears again.



Step 17. Click **Close** to return to the main screen and then **Exit the EL-CID program.**